

# Sparkle Suede

Table Topper design by Cyndi Hershey




Table topper size: approximately 43½" x 43½"



Featuring fabrics from  
Sparkle Suede collection by P&B Textiles



# Sparkle Suede

Fabric collection by P&B Textiles

Original Table Topper design by Cyndi Hershey

Skill level: Intermediate • Finished Topper Size: approximately 43½" x 43½"

## Yardages:

RED/GREEN:	
Fabric A: <b>SPAR 302 R</b> .....	1/4 yard
Fabric B: <b>SPAR 303 E</b> .....	1/3 yard
Fabric C: <b>SPAR 304 HG</b> .....	3/8 yard
Fabric D: <b>SPAR 305 R</b> .....	1/3 yard
Fabric E: <b>SPAR 302 K</b> .....	1/4 yard
Fabric F: <b>SPAR 304 W</b> .....	1 yard
Backing: <b>SPAR 303 HG</b> .....	3 yards
Batting .....	50" square

BLUE:	
<b>SPAR 302 WS</b> .....	1/4 yard
<b>SPAR 303 LB</b> .....	1/3 yard
<b>SPAR 304 N</b> .....	3/8 yard
<b>SPAR 305 WS</b> .....	1/3 yard
<b>SPAR 302 N</b> .....	1/4 yard
<b>SPAR 304 LB</b> .....	1 yard
<b>SPAR 303 N</b> .....	3 yards
Batting .....	50" square

## Cutting Instructions:

Please read all instructions carefully before beginning. Strips are cut across the width of fabric unless otherwise stated. All seams are sewn with a 1/4" seam unless otherwise stated.

### From Fabric A:

1. Cut one 3 1/2" strip.

### From Fabric B:

1. Cut two 3 1/2" strips.

### From Fabric C:

1. Cut three 3 1/2" strips.

### From Fabric D:

1. Cut two 3 1/2" strips.

### From Fabric E:

1. Cut one 3 1/2" strip.

### From Fabric F:

1. Cut two 19 1/4" squares, sub cut diagonally in both directions to yield eight quarter-square triangles.
2. Cut four 2 1/4" strips for binding

## Piecing Instructions:

### Strip Set #1

1. Sew one 3 1/2" strip each of A, B and C together as shown in Figure 1. Indent each strip by 3" in order to make use of the full width of strip set when cutting into segments. Press seams toward A strip. **TIP:** It is very important that you press from the right side of the strip set and check to be sure that none of the strips are rolled over causing pleats. You need sharp, clean seams to ensure accurate segments. Using spray sizing when pressing strip sets can help to add body to the fabric making it easier to cut sets into segments. Align the 45 degree angle line of your ruler with a seam. Cut end of strip set at an angle keeping cut as close to end of strips as possible. Beginning at the trimmed, angled edge of the strip set, cut eight 3 1/2" segments. Keep checking that you are maintaining the correct angle. You may need to retrim the 45-degree angled end. If so, be sure to trim only the narrowest amount necessary.




Figure 1

### Strip Set #2

2. Sew one 3 1/2" strip each of B, C and D in same manner. Press seams toward D strip. Cut segments as for Strip Set #1.

### Strip Set #3

3. Sew one 3 1/2" strip each of C, D and E in same manner. Press seams toward E strip. Cut segments as for Strip Set #1.
4. Sew one segment from each strip set into a diamond (Figure 2). Match the 1/4" seam points of each segment at each seam intersection and pin. There will be a point extending at the beginning and end of the seam line. Be sure that those points are positioned properly to allow for an accurate 1/4" seam when sewing through the "V" that is formed at both ends. Repeat to make eight diamonds. Press the seams of four diamonds in one direction (X diamonds) and the remaining four diamonds in the opposite direction (Y diamonds).




Figure 2 **Make 8.**

5. Sew one X and one Y diamond together nestling seams together (seams should face in opposite directions). Leave the outer end of the seam open 1/4" to allow for inserting the setting triangle. Sew completely through the end at the center seam end. Press seam open. Repeat to make four double-diamonds.
6. Sew two double-diamonds together into a half-star leaving outer end of seam open 1/4". Press seam open. Repeat.
7. Sew half-diamonds together to complete star leaving both ends open 1/4".
8. With right sides together, place one 19 1/4" F triangle over a star point matching the tips of both. Pin sides together matching 1/4" seam point at inside corner. Starting at center and beginning at 1/4" seam allowance, sew seam to outside point. Repeat for remaining side of triangle. Press seams toward the triangle. Repeat for remaining triangles.

### Finishing:

1. Cut two 50" backing pieces. Sew together on a long edge with a 1/2" seam allowance. Press seam open. Trim to 50" square.
2. Layer backing, batting and quilt top. Baste layers together.
3. Quilt as desired.
4. Trim layers even with top.
5. Join four 2 1/4" F binding strips with diagonal seams. Press seams open. Press strip in half lengthwise with wrong sides together to make double-fold binding. Sew binding to quilt using your favorite method. The outside angles are 135 degrees – not 90 degrees as on a typical quilt. When sewing binding to the front of the quilt, stop at the seam point as you would normally do. Turn quilt and align raw edges of binding and quilt; continue to sew. When turning binding to back, you will need to fold the binding to create a "point".
6. Make a label and sew to back of the topper.




Table Topper Diagram

# Sparkle Suede

Fabric Collection  
by P&B Textiles



SPAR 302 W



SPAR 303 W



SPAR 304 W\*



SPAR 305 W




SPAR 302 E



SPAR 303 E\*



SPAR 304 E



SPAR 305 E



SPAR 302 HG




SPAR 303 HG †



SPAR 304 HG\*



SPAR 305 HG



SPAR 302 R\*




SPAR 303 R



SPAR 304 R



SPAR 305 R\*



SPAR 302 K\*



SPAR 303 K



SPAR 304 K



SPAR 305 K



SPAR 302 WS\*



SPAR 303 WS



SPAR 304 WS



SPAR 305 WS\*



SPAR 302 LB



SPAR 303 LB\*



SPAR 304 LB\*



SPAR 305 LB



SPAR 302 N\*



SPAR 303 N†



SPAR 304 N\*



SPAR 305 N

# Sparkle Suede

Stocking design by Lucy A. Fazley



Stocking size: approximately 10.75" x 15.5"



Featuring fabrics from  
Sparkle Suede collection by P&B Textiles



P&B Textiles • pbtex.com • 800-351-9087 • 45 Washington Street, Pawtucket, RI 02860

# Sparkle Suede

Fabric collection by P&B Textiles

Original Stocking design by Lucy A. Fazley

Skill level: Confident Beginner • Finished Stocking Size: approximately 10 3/4" x 15 1/2"

## Yardages for one stocking:

### RED/GREEN:

Fabric A: **SPAR 302 HG** ..... 1/2 yard  
Fabric B: **SPAR 302 K** ..... 1/8 yard  
FOR PATCHWORK BODY: 1/8 yard of each color:  
**SPAR 302 E, HG, R; SPAR 303 E, HG, R**  
**SPAR 304 E, HG, R; SPAR 305 E, HG, R**  
Fusible web:..... 1/2 yard

### BLUE:

Fabric A: **SPAR 303 N** ..... 1/2 yard  
Fabric B: **SPAR 302 WS**..... 1/8 yard  
FOR PATCHWORK BODY: 1/8 yard of each color:  
**SPAR 302 LB, N, WS; SPAR 303 LB, N, WS**  
**SPAR 304 LB, N, WS; SPAR 305 LB, N, WS**  
Fusible web: ..... 1/2 yard

## Cutting Instructions:

Please read all instructions carefully before beginning. Strips are cut across the width of fabric unless otherwise stated. All seams are sewn with a 1/4" seam unless otherwise stated. Prepare complete stocking template and heel and toe templates.

### From Fabric A:

1. Cut one 11" strip. Sub cut one 11" x 13 3/4" strip for cuff.
2. Reserve rest of fabric for heels and toes.

### From Fabric B:

1. Cut one 1" strip. Sub cut one 1" x 13 3/4" strip for accent.
2. From remainder: cut 1" x 6 1/2" strip for hanger.

### From rest of fabric:

1. Cut one 2 1/2" strip from each fabric. Sub cut eight 2 1/2" squares from each strip. You will have extra squares.

## Piecing Instructions:

### A. Patchwork Body of Stocking

1. Arrange thirty-six 2 1/2" squares as you wish.
2. Sew six 2 1/2" squares into a row. Press to the left. Make 6 rows. Press rows in opposite directions.
3. Sew six rows into a 12 1/2" x 12 1/2" block. Make two blocks (Figure 1).





Figure 1



Make 2.

4. Position Stocking Template on block. Pin securely. Cut one stocking body (Figure 2). Reverse template and pin to second block. Cut one reverse stocking body.




Figure 2

### B. Heel and Toe

1. Trace heel template and toe template once each on paper side of fusible web leaving about 1/4" between tracings. Also trace one reverse heel template and one reverse toe template.

- Place tracings web side down on wrong side of Fabric A. Lightly fuse in place. Cut out each piece along marked lines.
- Place appliqué pieces on stocking bodies as shown (Figure 3). Fuse in place following web manufacturer's instructions. Stitch around inner edges of appliqué pieces.




Figure 3

### Stocking Assembly:

- Place stocking pieces right sides together aligning all edges. Stitch all but top edge with a 1/4" seam allowance (Figure 4). Clip inner curves, trim outer curves. Press seam open as much as possible. Turn right side out and press flat.
- Stitch Fabric B accent piece short edges right sides together with 1/4" seam. Repeat to join 11" ends of Fabric A cuff (Figure 5). Press seams open.




Figure 4




Figure 5

- Turn B piece right side out. Fold in half lengthwise, right side out, so it is 1/2" wide (Figure 6).



Figure 6

- Slide Fabric B accent over top of stocking, aligning raw edges at top. Align seam allowances. Folded edge of accent should be on bottom (Figure 7). Pin or baste in place.
- Slide Fabric A cuff over top of stocking and accent strip with right sides together. Align raw edges on top. Align seam allowances. Sew through all layers at top edge with a 1/4" seam (Figure 8).




Figure 7




Figure 8

- Press Fabric A cuff and seam upward. The Fabric B accent strip will form a flat piping that lays over the top of the stocking. Fold top of cuff edge 3/4" to the inside (Figure 9). Press.
- Fold Fabric A to the inside so the folded edge covers the seam between stocking and cuff. Press. Pin in place. Topstitch through all layers from outside of stocking, between the flat piping and cuff.




Figure 9

### Finishing:

- Fold the 1" ends of the 1" x 6 1/2" Fabric B strip under 1/4" and press. Fold the strip in half lengthwise. Open and fold each long raw edge to center then refold in half. Topstitch along long side and across both ends to create the 1/4" x 6" hanging tab (Figure 10).
- Fold the hanging tab in half so it is about 3" long (Figure 11).
- Place the folded end inside the stocking over the side seam so enough sticks out above the stocking to use as a hanger. Stitch in place (Figure 12).



Figure 10



Figure 11






Figure 12




Scale Check for pdf files. When you print these templates, this ruler should measure 2 inches long. If it does not, change, "page scaling" to "none" in the print dialog box.




### Toe Template

100%  
Trace 1 and 1 reverse



### Stocking Template 1 of 3






1


**Stocking Template  
2 of 3**

2


**Heel Template**  
100%  
Trace 1 and 1 reverse



**Scale Check for pdf files.**  
When you print these templates, this ruler should measure 2 inches long. If it does not, change, "page scaling" to "none" in the print dialog box.



Scale Check for pdf files. When you print these templates, this ruler should measure 2 inches long. If it does not, change, "page scaling" to "none" in the print dialog box.



**Stocking Template**  
**3 of 3**

**2**

# Sparkle Suede

Fabric Collection  
by P&B Textiles



SPAR 302 W



SPAR 303 W



SPAR 304 W



SPAR 305 W




SPAR 302 E\*



SPAR 303 E\*



SPAR 304 E\*



SPAR 305 E\*



SPAR 302 HG\*



SPAR 303 HG\*



SPAR 304 HG\*



SPAR 305 HG\*



SPAR 302 R\*




SPAR 303 R\*



SPAR 304 R\*




SPAR 305 R\*



SPAR 302 K



SPAR 303 K\*



SPAR 304 K



SPAR 305 K



SPAR 302 WS\*



SPAR 303 WS\*



SPAR 304 WS\*



SPAR 305 WS\*



SPAR 302 LB\*



SPAR 303 LB\*



SPAR 304 LB\*



SPAR 305 LB\*



SPAR 302 N\*



SPAR 303 N\*



SPAR 304 N\*



SPAR 305 N\*